

## LifePoint - System Requirements

IBM Compatible Workstation Requirements		
	Minimum	Preferred
Processor	Pentium II, 400 MHz	2 GHz Processor
Memory	256 MB RAM	1 GB RAM
Display Settings	Resolution at 800x600pixels. Font size set to Small fonts.	Resolution at 1024x768pixels. Font size set to Small fonts.

Software Requirements	
Platforms/Operating Systems	32-bit Windows 7, Vista, XP, NT, ME, 2000 or 98. Windows versions not supported: Windows CE, Windows XP Embedded or any other scaled down version of Windows.
Browsers	Internet Explorer (IE) 8.x/7.x/5.5/5.0 with 128-bit encryption using the default settings. JavaScript must be enabled.
Communications	There are no specifications for how users connect to the Internet; however, if connecting via modem to an ISP, a 56K modem is recommended.

Before you sign on to Lifepoint for the first time, please do the following:

After opening Internet Explorer, on the **Tools** menu, select **Internet Options**.

On the **General** tab:

1. Go to the **Temporary Internet Files** section.
2. Click the **Delete Files** button.
3. Select the **Delete All Offline Content** check box.
4. Click **OK** (may take a few minutes).
5. Go to [www.lifepointlink.com/wdl](http://www.lifepointlink.com/wdl)
6. In the left **Navigation Bar**, click the **Mead ScriptX Print Control** hyperlink.
7. Follow the prompts to install the Web Print Drivers.
8. In the left **Navigation Bar**, click the **Trusted Sites Setup** hyperlink.
9. At the bottom of the screen, click **Run**.
10. On the **Add Trusted Site** window, click **Add**.

## To request additional user names and passwords:

- Contact your Dynacare Sales Representative for a LifePoint Access Request Form

## Signing On

1. Go to [www.lifepointlink.com/dynacare](http://www.lifepointlink.com/dynacare)
2. In the **Navigation Bar** on the left, click **Login Page**.
3. Enter your location code.
4. Enter your user name and the default password provided by Dynacare Laboratories.
5. Click **Submit**.

## Changing Passwords

1. LifePoint prompts you to change your password at the first login.
2. Click **Change Password** - *Passwords are case sensitive.*
3. Enter old password, press Tab key.
4. Enter new password, press Tab key.
5. Enter new password again.
6. Click **Submit**.